

Release Notes

Email Security

Anti-Spam Desktop Software

System Compatibility

SonicWALL Anti-Spam Desktop Software is supported on systems with the following:

Operating System	Mail Clients		
Windows 7 (32- & 64-bit)	Outlook 2007	Outlook 2003	
Vista (32 & 64)	Outlook 2007	Outlook 2003	Windows Mail ¹
Windows XP	Outlook 2007	Outlook 2003	Outlook Express 6.0

Enhancements

The following is a list of enhancements made to features in the SonicWALL Anti-Spam Desktop 6.2:

- Support for Windows 7 32-bit and 64-bit versions
- Enhanced effectiveness against the latest spam and other email-borne threats

¹ Excluding IMAP support for Windows Mail

Release Notes

Known Issues

The following is a list of known issues in the SonicWALL Anti-Spam Desktop 6.2 Software release:

	Symptom	Condition

Release Notes

New Features in 6.2

The following new features have been added to version 6.2. This section contains a brief synopsis of each one: the full feature is described in the documentation.

Microsoft Windows 7 32- and 64-bit Support

SonicWALL now supports both the 32-bit and 64-bit versions of Microsoft Windows 7. Be sure that the link you chose to install Anti-Spam Desktop corresponds to the system you are installing on.

Enhanced Effectiveness

SonicWALL now delivers the latest anti-spam technology used in our corporate gateway products with Anti-Spam Desktop 6.2. This provides enhanced effectiveness against the latest spam and email-borne threats.

Installing ASD 6.2

To install Anti-Spam Desktop, first obtain a download link and license key.

1. Click the link provided to start the download process. Depending on your browser settings, you may be asked to approve the download. The size of the downloaded file is 7-8 MB.
2. Once the download is complete, open the downloaded file and approve running it. The installation process begins, and will take 5 minutes or less.
3. Log out of your system and log back in again to activate Anti-Spam Desktop.
4. Open the License window by selecting the *Buy Now* button from the Windows System Tray or the Toolbar menu. The Buy SonicWALL Anti-Spam Desktop dialog box displays.
5. Enter the license key to SonicWALL Anti-Spam Desktop in the space provided. License keys are case sensitive and entered in a sequence of 24 letters in groups of four, for example: aaaa-bbbb-cccc-dddd-eeee-ffff.

Anti-Spam Desktop will always start automatically, and you can access the settings using the SonicWALL logo located in the system tray and in your mail application tool bar.

NOTE: *You do not need to configure SonicWALL Anti-Spam Desktop.* It automatically adapts to your preferences. On first use, Anti-Spam Desktop scans your Sent Items folder to include your known recipients in your Allowed list. When you choose to junk a message, SonicWALL Anti-Spam Desktop puts the sender's email address in your Blocked List.

Your license includes dynamic spam signature file updates, product upgrades, and email support for one, two, or three years. (Note: Users who purchase SonicWALL Anti-Spam Desktop from the web receive their license key via email.)

Document part number: 232-001813-00 Rev A
Last updated: 12/11/2009